



## Checking the software versions

Before beginning to update the software, check the software version of the US-1x2 being used.

For details about how to check the software version, see “Opening the Settings Panel” in “5 – Using the Settings Panel” of the Reference Manual.



Windows Settings Panel Home page



Mac Settings Panel

## Procedures for updating the computer software

### Preparing

- If the latest software has already been installed, there is no need to update it. Use it as is.
- Run Windows Update to use the latest system version.
- Disconnect all cables from the unit except for the power cord.
- Set the phantom power switch to off.

### Updating the Windows driver and the Mac Settings Panel

#### Updating the Windows dedicated software and the Mac dedicated software

##### For Windows

1. Download the latest Windows dedicated software for the operating system you are using from the TEAC Global Site (<http://teac-global.com/>) and save it on the computer to be used with the unit.
2. Uncompress the saved software (zip file) on the computer desktop or another location.
3. Double-click the “TASCAM\_US-1x2\_Installer\_x.xx.exe” file in the folder that appears after uncompression to automatically launch the installation software.
4. After this, follow the installation procedures in “Installing the Windows dedicated software” in the Owner’s Manual.

##### For Mac

#### NOTE

Depending on the Gatekeeper setting, a warning message might appear during installation. For information about Gatekeeper, see “Note about Gatekeeper” of the Reference Manual.

1. Download the latest Settings Panel for the operating system you are using from the TEAC Global Site (<http://teac-global.com/>) and save it on the computer to be used with the unit.
2. Double-click “TASCAM\_US-1x2\_Installer\_x.xx.dmg”, which is the saved disk image file for the Mac dedicated software, and double-click “US-1x2\_Installer.pkg” inside the folder that opens.

#### NOTE

Depending on the computer’s settings, the downloaded ZIP file might not have opened automatically. In this case, unzip the ZIP file to access the disk image file.

3. When the installer starts, click the “Continue” button.
4. After this, follow the installation procedures in “Installing the Mac dedicated software” in the Owner’s Manual.